

Installation de Proxmox

1 ère étape: Rendez-vous sur [proxmox.com](https://www.proxmox.com) onglet Téléchargements et télécharger la version la plus récente.

 Proxmox
<https://www.proxmox.com> > ... · Traduire cette page

Proxmox - Powerful open-source server solutions

Proxmox Virtual Environment is a complete open-source platform for enterprise virtualization. With the built-in web interface you can easily manage VMs and ...

Downloads

**Proxmox VE 8.4 ISO Installer**

Version	File Size	Last Updated	Download
8.4-1	1.57 GB	April 09, 2025	Torrent
SHA256SUM d237d70ca48a9f6eb47f95fd4fd337722c3f69f8106393844d027d28c26523d8			

2ème étape: Installez Ventoy pour faire une clé bootable en se rendant sur <https://www.lesnumeriques.com/telecharger/ventoy-51498>

Ventoy

≡ CATÉGORIES



Licence gratuite
Ventoy

 Télécharger

Ventoy est une application Open Source et gratuite qui vous permet de créer facilement et rapidement une clé USB bootable sans avoir besoin de connaissances avancées en informatique.

Sommaire :


Pourquoi utiliser Ventoy ?

Quelles sont les nouveautés de la dernière version de Ventoy ?

Avec quels OS Ventoy est-il compatible ?

Quelles sont les meilleures alternatives à Ventoy ?


3ème étape: Lancez Ventoy pour formater la clé USB en tant que clé bootable Ventoy



4ème étape: Mettre l' ISO que l'on souhaite dans la clé

> Ventoy (D:)				
	Nom	Modifié le	Type	Taille
e	proxmox-ve_7.4-1	26/05/2025 12:21	Fichier d'image dis...	1 096 544 ...


5ème étape: Boot sur la clé




6ème étape: Choisir ISO proxmox




7ème étape: Choisir "Normal Mode" ou "grub2 mode"




8ème étape: Lancez le programme d'installation de Proxmox




9ème étape: Acceptez l'EULA (Contrat d'utilisateur Final)



10ème étape: Choisir le pays pour la disposition du clavier et la langue



11ème étape: Mettre un mot de passe



12ème étape: Mettre les bons paramètres réseaux



Proxmox VE Installer

Management Network Configuration

Please verify the displayed network configuration. You will need a valid network configuration to access the management interface after installation.

Afterwards press the Next button. You will be shown a list of the options that you chose during the previous steps.

- **IP address:** Set the IP address for your server.
- **Netmask:** Set the netmask of your network.
- **Gateway:** IP address of your gateway or firewall.
- **DNS Server:** IP address of your DNS server.

Management Interface: ens18 - ba:33:cf:2f:a9:2f (virtio_net) ▼

Hostname (FQDN): nodes1.yourdomain.tld

IP Address: 192.168.1.57

Netmask: 255.255.255.0

Gateway: 192.168.1.1

DNS Server: 192.168.1.1

Abort

Previous

Next

13ème étape: Résumé de la configuration de Proxmox



Proxmox VE Installer

Summary

Please verify the displayed informations. Once you press the **Install** button, the installer will begin to partition your drive(s) and extract the required files.

Option	Value
Filesystem:	ext4
Disk(s):	/dev/sda
Country:	France
Timezone:	Europe/Paris
Keymap:	fr
E-Mail:	un_mail@domaine
Management Interface:	enp0s3
Hostname:	pve

Abort

Previous

Install

14ème étape: Lancez l'installation de Proxmox



Proxmox VE Installer

Proxmox VE Cluster

With **Proxmox VE** you can join multiple physical servers to one VE Cluster.

This flexible multi-master cluster eliminates a single point of failure.

- **Central management**
Create and manage new Virtual Servers by simply selecting the node where it should run.
- **Proxmox Cluster file system (pmxcfs)**
Database-driven file system for storing configuration files, replicated in realtime on all nodes using corosync.

extracting pve-qemu-kvm_6.0.0-2_amd64.deb
71%